

Parallels[®] Plesk Control Panel

Parallels Plesk Control Panel 8.6 for Linux/Unix Acronis True Image Server Module Administrator's Guide

Copyright Notice

ISBN: N/A

Parallels

660 SW 39th Street

Suite 205

Renton, Washington 98057

USA

Phone: +1 (425) 282 6400

Fax: +1 (425) 282 6444

© Copyright 1999-2008,

Parallels, Inc.

All rights reserved

Distribution of this work or derivative of this work in any form is prohibited unless prior written permission is obtained from the copyright holder.

Patented technology protected by U.S. Patents 7,328,225; 7,325,017; 7,293,033; 7,099,948; 7,076,633.

Patents pending in the U.S.

Product and service names mentioned herein are the trademarks of their respective owners.

Contents

Preface	4
<hr/>	
Typographical Conventions	4
Feedback	5
About Acronis True Image Server Management Module	5
<hr/>	
Installing ATIS Management Module	7
<hr/>	
Installation Requirements	7
Installing ATIS Management Module	8
Using ATIS Management Module	9
<hr/>	
Logging Into Module	9
Creating Backup Image	10
Managing Scheduled Backup Tasks	12
Viewing Status of Running Tasks	15
Restoring Data	15

Preface

In this section:

Typographical Conventions	4
Feedback	5

Typographical Conventions

Before you start using this guide, it is important to understand the documentation conventions used in it.

The following kinds of formatting in the text identify special information.

<u>Formatting convention</u>	<u>Type of Information</u>	<u>Example</u>
Special Bold	Items you must select, such as menu options, command buttons, or items in a list.	Go to the System tab.
<i>Italics</i>	Titles of chapters, sections, and subsections. Used to emphasize the importance of a point, to introduce a term or to designate a command line placeholder, which is to be replaced with a real name or value.	Read the Basic Administration chapter. The system supports the so called <i>wildcard character</i> search.
Monospace	The names of commands, files, and directories.	The license file is located in the <code>http://docs/common/licenses</code> directory.

Preformatted	On-screen computer output in your command-line sessions; source code in XML, C++, or other programming languages.	# ls -al /files total 14470
Preformatted Bold	What you type, contrasted with on-screen computer output.	# cd /root/rpms/php
CAPITALS	Names of keys on the keyboard.	SHIFT, CTRL, ALT
KEY+KEY	Key combinations for which the user must press and hold down one key and then press another.	CTRL+P, ALT+F4

Feedback

About Acronis True Image Server Management Module

If you have found a mistake in this guide, or if you have suggestions or ideas on how to improve this guide, please send your feedback using the online form at <http://www.parallels.com/en/support/usersdoc/>. Please include in your report the guide's title, chapter and section titles, and the fragment of text in which you have found an error.

The Plesk-integrated Acronis True Image Server management module (hereafter referred to as the ATIS management module) provides a graphical interface to manage the Acronis True Image Server (ATIS) for Linux application installed on the same Plesk-enabled server. Acronis True Image Server creates server disk backup images without interrupting server operations and allows for easy and fast recovery of the entire system.

Using this ATIS management module, the Plesk administrator can schedule backup tasks, launch manually backup tasks, select the compression level for backup images, set up passwords to protect backup images, etc.

This document describes how to work with the ATIS module for Plesk. Therefore, this guide does not cover the entire ATIS functionality. If you have questions related to the use of the Acronis True Image Server application, please refer to the relevant documentation.

Installing ATIS Management Module

This chapter describes how to install the ATIS management module on a server where Plesk is installed.

In this chapter:

Installation Requirements	7
Installing ATIS Management Module	8

Installation Requirements

For normal operation of the ATIS module, your server must meet the following hardware and software requirements:

- Plesk version 8.0 or later

Acronis True Image Server for Linux version 8.0 or later, installed on the same server where Plesk is installed

- 3 MB of disk space available
- One of the operating systems supported by Acronis True Image Server *for Linux*

Note: You must install and configure Acronis True Image Server independently of the Plesk-integrated management module. You must also have a valid license key for the ATIS application. You can purchase and install this license key through Plesk control panel (**Server > License Management > Order Control Panel Add-ons**). If Acronis True Image Server for Linux is not installed on your Plesk-enabled server, you can still install the ATIS management module but cannot use it.

Important:

- The ATIS management module and Acronis True Image Server application cannot be used in Virtuozzo virtual environments.
- The ATIS management module does not run under the FreeBSD operating system because the Acronis True Image Server application does not support FreeBSD.

Installing ATIS Management Module

You can install the module using one of the two methods:

- using the module management feature available in the Plesk control panel
- from the command line

➤ **To install the module from the Plesk control panel:**

1 In the Plesk navigation pane, click **Modules**.

2 Under **Tools**, click  **Manage Modules**.


3 Click  **Add Module**.

4 On the **Upload New Module** page, enter the path to the module package file or use **Browse...** to locate the file.

The module package must have either the `.rpm` or `.deb` extensions.

5 Click **OK**.

The package will be extracted and installed to the proper location. After installation,

the module appears as the  **Acronis True Image Server Management Module** button on the **Modules** page.

➤ **To install the module from the command line:**

To install from the `.rpm` package:

- Run the `.rpm` package using the `rpm -Uhv *.rpm` command.

To install from the `.deb` package:

- Run the `.deb` package using the `dpkg -i *.deb` command

Using ATIS Management Module

This chapter describes how to manage the Acronis True Image Server *for Linux* application using the ATIS management module interface.


In this chapter:

Logging Into Module.....	9
Creating Backup Image.....	10
Managing Scheduled Backup Tasks	12
Viewing Status of Running Tasks	15
Restoring Data	15

Logging Into Module


You can log into the ATIS management module only if you are logged under the Plesk administrator's account.


➤ *To log into the ATIS management module:*

- 1 In the Plesk navigation pane, click **Modules**.
- 2 Click the  **Acronis True Image Server management module for Plesk** icon to start managing the ATIS application.

Creating Backup Image

➤ To create a backup image of your server disk:

- 1 On the **Tasks** tab of the ATIS module main page, click  **Backup Now**.
- 2 Under **Partitions for backup**, select the hard disk partition for which want to create a backup file.



Modules > Acronis TrueImage >

Backup now [Up Level](#)


Partitions for backup *

Partition	Mount point	File system type
<input checked="" type="checkbox"/> hda1	/	Ext3
<input type="checkbox"/> hda5	/usr	Ext3
<input checked="" type="checkbox"/> hda6	/var	Ext3

Figure 1: Selecting partitions for backup

The list of partitions shows the hard disk structure of your server, including the relative path point and the type of disk file systems (**Mount point** and **File system type** column). You must select at least one partition for backup. You can select a random set of partitions.

- 3 Under **Backup settings**, specify the following settings of backing up:



Backup settings

Path to storage *

Backup file name * Filename must be less than 200 symbols length, contain only latin symbols, digits, symbols "-", "_", and first symbol must be letter.

Send report to e-mail *

Compression level * ▼

Incremental backup

Figure 2: Selecting backup options

- **Path to storage** - Enter the path to an existing directory where backup file will be saved; for example, `/backup` or `/var/backup`.

You can configure Acronis True Image Server to save backup files on both hard and removable drives.

- **Backup file name** - Type the name of the backup file.

The name can contain only latin symbols, digits, and “-_,.” symbols. The name must start with a letter only. The maximum number of symbols is 200.

- **Send report to e-mail** - Specify an e-mail address that will be used to send reports on the results of backup creation (both successful and unsuccessful).
- **Compression level** - Select the compression level for the backup file.

The items in this drop-down list range from 0 (no compression) to 9 (maximum compression). If you select 0, the backup will be imaged without any compression, which will increase the backup file size. If you select the maximum compression level, it will take longer for the application to create the backup. It is recommended that you set the compression level to medium values, for example 4 or 5.

- **Incremental backup** - Select this check box to create an incremental backup file. Leave this check box blank to create a complete backup of the selected partition(s).

Complete backup images contain all sectors within the selected partition(s), including operating system files and your data. Incremental backup images include only the data that has changed since the last time a backup was created. Incremental backup file names are created as follows: if the first complete backup file is `tmp.tib`, the subsequent incremental backup files will be named as `tmp1.tib`, `tmp2.tib`, etc.

Thus, if you are creating a backup for this partition(s) for the first time or you have made significant changes to the system after the last time the backup was created, it is better to create a complete backup. If you have recently created a backup image of the selected partition(s), incremental backup is recommended.

- 4 Select the **Use password protection** check box to protect the backup file with a password and enter your password in the fields below.


The maximum password length is 30 symbols.


- 5 Click **OK**.

Managing Scheduled Backup Tasks

Using the ATIS management module interface, you can schedule crontab to start backup imaging tasks at specified time. The tasks will be performed by the ATIS application installed on your server.

➤ **To schedule a new backup task:**

- 1 On the **Tasks** tab of the ATIS module main page, click  **Schedule New Backup**.
- 2 Under **Backup time**, specify the schedule for the backup task:



Modules > Acronis TrueImage >

Create new backup task [Up Level](#)

Backup time


Period * Weekly

Backup day * Sun

Backup time * 21 Hours 21 Minutes

Figure 3: Setting up backup task schedule

- In the **Period** box, select the frequency of task performance.
If you set the frequency to *weekly* or *monthly*, select the **Backup day** from the list below.
 - In the **Backup time** box, specify the time for task launch.
- 3 Specify other settings for the scheduled backup task:
 1. Under **Partitions for backup**, select the hard disk partition for which want to create a backup file.



Partitions for backup *

Partition	Mount point	File system type
<input checked="" type="checkbox"/> hda1	/	Ext3
<input type="checkbox"/> hda5	/usr	Ext3
<input checked="" type="checkbox"/> hda6	/var	Ext3

Figure 4: Selecting partitions for backup

The list of partitions shows the hard disk structure of your server, including the relative path point and the type of disk file systems (**Mount point** and **File system type** column). You must select at least one partition for backup. You can select a random set of partitions.

2. Under **Backup settings**, specify the following settings of backing up:

The screenshot shows a 'Backup settings' form with the following fields and values:

- Path to storage ***: /hda5
- Backup file name ***: ATIS_backup. A note below the field states: 'Filename must be less than 200 symbols length, contain only latin symbols, digits, symbols "-_," and first symbol must be letter.'
- Send report to e-mail ***: johndoe@myserver.com
- Compression level ***: 3 (default compression) [dropdown menu]
- Incremental backup**:

Figure 5: Selecting backup options


- **Path to storage** - Enter the path to an existing directory where backup file will be saved; for example, /backup or /var/backup.
You can configure Acronis True Image Server to save backup files on both hard and removable drives.
- **Backup file name** - Type the name of the backup file.
The name can contain only latin symbols, digits, and “-_.,” symbols. The name must start with a letter only. The maximum number of symbols is 200.
- **Send report to e-mail** - Specify an e-mail address that will be used to send reports on the results of backup creation (both successful and unsuccessful).
- **Compression level** - Select the compression level for the backup file.
The items in this drop-down list range from 0 (no compression) to 9 (maximum compression). If you select 0, the backup will be imaged without any compression, which will increase the backup file size. If you select the maximum compression level, it will take longer for the application to create the backup. It is recommended that you set the compression level to medium values, for example 4 or 5.
- **Incremental backup** - Select this check box to create an incremental backup file. Leave this check box blank to create a complete backup of the selected partition(s).
Complete backup images contain all sectors within the selected partition(s), including operating system files and your data. Incremental backup images includes only the data that have changed since the last time a backup was created. Incremental backup file names are created as follows: if the first complete backup file is tmp.tib, the subsequent incremental backup files will be named as tmp1.tib, tmp2.tib, etc.
Thus, if you are creating a backup for this partition(s) for the first time or you have made significant changes to the system after the last time the backup was created, it is better to create a complete backup. If you have recently created a backup image of the selected partition(s), incremental backup is recommended.

3. Select the **Use password protection** check box to protect the backup file with a password and enter your password in the fields below.

The maximum password length is 30 symbols.

4. Click **OK** to create a scheduled backup task.


After the scheduled task creation procedure is complete, the backup creation task will appear in the list of scheduled backup tasks and in the list of cron tasks for superuser (root).



The screenshot shows a web interface titled "Tasks list". At the top, there is a search bar, a "Search" button, and a "Show All" button. On the right, there is a "Remove Selected" button with a red 'X' icon. Below the search bar, it says "1 Tasks total" and "Number of entries per page: 10 25 100". The main part of the interface is a table with the following columns: "Period", "Backup time", "Path to storage", and "Partitions for backup". There is a checkbox in the rightmost column of each row. The table contains one row with the following data: "Weekly", "Every Sun at 21:21:00", "/usr", and "sda1". Below the table, it says "1 Tasks total" and "Number of entries per page: 10 25 100".

Period ▲	Backup time	Path to storage	Partitions for backup	<input type="checkbox"/>
Weekly	Every Sun at 21:21:00	/usr	sda1	<input type="checkbox"/>

Figure 6: List of scheduled backup tasks

Note: To view the task in crontab, select **Server** in the navigation pane and click  **Crontab** on the Server administration page.

➤ **To remove a scheduled backup task:**

1. In the list of tasks, select the check box that corresponds to the task you want to delete and click **Remove Selected**.
2. On the next page, confirm task removal and click **OK**.

The task will be removed from the list of scheduled backup tasks in the module and from the cron tasks.

➤ **To edit settings of a scheduled backup task:**


- Click the frequency of the task in the **Period** column and edit task settings on the next page.


Viewing Status of Running Tasks

➤ *To view the status of running backup creation task:*

- 1 On the ATIS Module main page, click the **Status** tab.

In the list below the running tasks are displayed. You can view the partition that is being backed up, the path to the backup file, and the task start time.

- 2 Click  **Refresh** to refresh the list of tasks.



The screenshot shows the ATIS Management Module interface. At the top, there is a breadcrumb 'Modules >' and the title 'Acronis TruImage Server Module'. Below the title are two tabs: 'Tasks' and 'Status', with 'Status' being the active tab. Underneath the tabs is a 'Tools' section containing a green circular refresh icon and the text 'Refresh'. Below the tools is a 'Running tasks' section which contains a table with the following data:

Partitions	Backup file	Start time
hda6	/home/ti/var.tib	2005-09-07 10:58:08 GMT

Figure 7: Viewing status of scheduled backup tasks

Restoring Data

➤ *To restore data from backup files:*

- 1 Log in to the server as root.
- 2 Issue the command `/usr/sbin/trueimage`.
Acronis True Image Server application interface opens.
- 3 Click the **Recovery** icon.
- 4 Click **Next >**.
- 5 Select the archive file.
- 6 Click **Next >**.
- 7 Specify the directory where you want to restore the data.
- 8 Click **Next >**.
- 9 Select files and directories to restore. You can choose to restore all data or browse the archive contents and select the desired directories and files. Click **Next >**.

- 10 Select the options for restoration process (that is, pre/post restoration commands, restoration process priority, and so on). You may use the default options or set the options manually.
- 11 Click **Next >**.
- 12 If you do not want to restore files of specific types from the archive, set the filters. You can apply custom filters, using the common masking rules. For example, to exclude all files with extension `.tib`, add `*.tib` mask. `My???.tib` mask will reject all `.tib` files with names, consisting of five symbols and starting with “my”.
- 13 Click **Next >**.
- 14 The next selection allows you to keep useful data changes, made since the selected backup. Choose what to do if the program finds in the target directory a file with the same name as in the archive:
 - **Overwrite existing file** – this will give the archived file unconditional priority over the file on the hard disk.
 - **Overwrite existing file if it is older** – this will give the priority to the most recent file modification, whether it is in the archive or on the disk.
 - **Do not overwrite existing file** – this will give the file on the hard disk unconditional priority over the archived file.
- 15 At the final step, the restoration summary is displayed. Up to this point, you can click **< Back** to make changes in the created task. Click **Proceed** to launch the task execution.
- 16 The task appears on the **Active tasks** pane of the main window. The task progress will be shown in the special window. You can stop the procedure by clicking **Cancel**. Please keep in mind that the aborted procedure still may cause changes in the destination directory.